

The image is a large, symmetrical, abstract graphic composed of the letters 'S' and 'Y' arranged in a grid-like pattern. The overall shape is a stylized 'Y' or a complex letter 'H'. The top part is a wide horizontal bar made of 'S's, with 'Y's forming a central vertical column. The sides are also made of 'S's, with 'Y's forming a central vertical column. The bottom part is a wide horizontal bar made of 'S's, with 'Y's forming a central vertical column. The entire graphic is composed of these two letters, creating a complex, symmetrical pattern.

```
DDDDDDDD  IIIIII  SSSSSSSS  MM  MM  000000  UU  UU  NN  NN  TTTTTTTTTT
DDDDDDDD  IIIIII  SSSSSSSS  MM  MM  000000  UU  UU  NN  NN  TTTTTTTTTT
DD  DD  II  SS  SSSSSSSS  MMMM  MMMM  00  00  UU  UU  NN  NN  TT
DD  DD  II  SS  SSSSSSSS  MMMM  MMMM  00  00  UU  UU  NN  NN  TT
DD  DD  II  SS  SSSSSSSS  MM  MM  00  00  UU  UU  NNNN  NN  TT
DD  DD  II  SSSSSS  MM  MM  00  00  UU  UU  NNNN  NN  TT
DD  DD  II  SSSSSS  MM  MM  00  00  UU  UU  NN  NN  TT
DD  DD  II  SS  MM  MM  00  00  UU  UU  NN  NN  TT
DD  DD  II  SS  MM  MM  00  00  UU  UU  NN  NN  TT
DD  DD  II  SS  MM  MM  00  00  UU  UU  NN  NN  TT
DD  DD  II  SS  MM  MM  00  00  UU  UU  NN  NN  TT
DDDDDDDD  IIIIII  SSSSSSSS  MM  MM  000000  UUUUUUUUUU  NN  NN  TT
DDDDDDDD  IIIIII  SSSSSSSS  MM  MM  000000  UUUUUUUUUU  NN  NN  TT

LL  IIIIII  SSSSSSSS
LL  IIIIII  SSSSSSSS
LL  II  SS
LL  II  SS
LL  II  SS
LL  II  SSSSSS
LL  II  SSSSSS
LL  II  SS
LL  II  SS
LL  II  SS
LL  II  SS
LLLLLLLLLL  IIIIII  SSSSSSSS
LLLLLLLLLL  IIIIII  SSSSSSSS
```

DISMOUNT
Table of contents

- DISMOUNT A MOUNTED MASS STORAGE^{E 3} VOLUME 16-SEP-1984 00:02:34 VAX/VMS Macro V04-00

Page 0

(3) 302
(4) 466
(5) 509

DISMOUNT FOREIGN DEVICE
DO_IO - COMMON I/O ROUTINE
DELETE_RUJ - DELETE RECOVERY UNIT JOURNAL


```
0000 1 .TITLE DISMOUNT - DISMOUNT A MOUNTED MASS STORAGE VOLUME
0000 2 .IDENT 'V04-000'
0000 3
0000 4
0000 5 *****
0000 6 *
0000 7 * COPYRIGHT (c) 1978, 1980, 1982, 1984 BY
0000 8 * DIGITAL EQUIPMENT CORPORATION, MAYNARD, MASSACHUSETTS.
0000 9 * ALL RIGHTS RESERVED.
0000 10 *
0000 11 * THIS SOFTWARE IS FURNISHED UNDER A LICENSE AND MAY BE USED AND COPIED
0000 12 * ONLY IN ACCORDANCE WITH THE TERMS OF SUCH LICENSE AND WITH THE
0000 13 * INCLUSION OF THE ABOVE COPYRIGHT NOTICE. THIS SOFTWARE OR ANY OTHER
0000 14 * COPIES THEREOF MAY NOT BE PROVIDED OR OTHERWISE MADE AVAILABLE TO ANY
0000 15 * OTHER PERSON. NO TITLE TO AND OWNERSHIP OF THE SOFTWARE IS HEREBY
0000 16 * TRANSFERRED.
0000 17 *
0000 18 * THE INFORMATION IN THIS SOFTWARE IS SUBJECT TO CHANGE WITHOUT NOTICE
0000 19 * AND SHOULD NOT BE CONSTRUED AS A COMMITMENT BY DIGITAL EQUIPMENT
0000 20 * CORPORATION.
0000 21 *
0000 22 * DIGITAL ASSUMES NO RESPONSIBILITY FOR THE USE OR RELIABILITY OF ITS
0000 23 * SOFTWARE ON EQUIPMENT WHICH IS NOT SUPPLIED BY DIGITAL.
0000 24 *
0000 25 *
0000 26 *****
0000 27
0000 28 ++
0000 29
0000 30 FACILITY:
0000 31
0000 32 MASS STORAGE DEVICE MANAGEMENT SUBROUTINES
0000 33
0000 34 ABSTRACT:
0000 35
0000 36 THIS ROUTINE DISMOUNTS THE INDICATED DEVICE.
0000 37
0000 38
0000 39 ENVIRONMENT:
0000 40
0000 41 VAX/VMS EXEC
0000 42 MODE = KERNEL
0000 43
0000 44
0000 45 AUTHOR: ANDREW C. GOLDSTEIN, CREATION DATE: 2-NOV-1977 14:10
0000 46
0000 47 MODIFIED BY:
0000 48
0000 49 V03-019 CDS0001 Christian D. Saether 28-Aug-1984
0000 50 Ignore SS$_VALNOTVALID errors when converting device
0000 51 lock.
0000 52
0000 53 V03-018 HH0049 Hai Huang 16-Aug-1984
0000 54 Call IOC$DALLOC_DMT routine to deallocate the device
0000 55 on dismount of a foreign volume.
0000 56
0000 57 V03-017 ACG0441 Andrew C. Goldstein, 13-Aug-1984 10:17
```

0000 58 : Issue both an IOS_UNLOAD and IOS_AVAILABLE to correctly
0000 59 : release tape drives.
0000 60 :
0000 61 : V03-016 ACG0441 Andrew C. Goldstein, 8-Aug-1984 11:33
0000 62 : Rework foreign volume dismount; locate all code in
0000 63 : this module. General code cleanup.
0000 64 :
0000 65 : V03-015 TMK0001 Todd M. Katz 21-Apr-1984
0000 66 : When deleting the logical name associated with a mounted volume,
0000 67 : delete the logical name block by calling LNMSDELETE_LNMB
0000 68 : instead of LNMSDELETE. Doing so will ensure that this deletion
0000 69 : takes place as if the system service \$DELLNM had been called
0000 70 : to delete the logical name. In other words, not only will the
0000 71 : target logical name be deleted, but so will all outer access
0000 72 : mode aliases.
0000 73 :
0000 74 : V03-014 LMP0221 L. Mark Pilant, 30-Mar-1984 13:48
0000 75 : Change UCB\$_OWNUI to ORB\$_OWNER and UCB\$_VPROT to
0000 76 : ORB\$_PROT.
0000 77 :
0000 78 : V03-013 ACG0371 Andrew C. Goldstein, 11-Nov-1983 9:32
0000 79 : Set PHY_IO in PCB privilege mask instead of PHD
0000 80 :
0000 81 : V03-012 LY0427 Larry Yetto 5-OCT-1983 14:51:12
0000 82 : If the DELJNL service call to delete the RU journal fails
0000 83 : then deassign the journal channel
0000 84 :
0000 85 : V01-011 TCM0005 Trudy C. Matthews 22-Sep-1983
0000 86 : If device is to be deallocated on dismount, don't do it here.
0000 87 : Wait until last channel deassign instead. This keeps the
0000 88 : device allocated and the lock present until all activity
0000 89 : has ceased from this mount.
0000 90 :
0000 91 : V03-010 TCM0004 Trudy C. Matthews 07-Sep-1983
0000 92 : Fix bug that caused foreign disks not to be unloaded on
0000 93 : dismount.
0000 94 :
0000 95 : V03-009 TCM0003 Trudy C. Matthews 22-Aug-1983
0000 96 : Undo change made in TCM0001. If a device is dismounted and
0000 97 : there are still channels assigned to it, we just want to
0000 98 : deallocate the local UCB. The cluster-wide lock (if it
0000 99 : exists) will be dequeued when the last channel is de-assigned.
0000 100 :
0000 101 : V03-008 TCM0002 Trudy C. Matthews 22-Jun-1983
0000 102 : Decrement refcount when a disk is dismounted. MOUNT has
0000 103 : been changed to increment the refcount while the disk
0000 104 : is mounted.
0000 105 :
0000 106 : V03-007 ADE9006 Alan D. Eldridge 01-MAY-1983
0000 107 : Restore PCB address (R4) on dismount of foreign devices.
0000 108 :
0000 109 : V03-006 STJ3103 Steven T. Jeffreys, 27-Apr-1983
0000 110 : Delete RUJ on dismount.
0000 111 :
0000 112 : V03-005 DMW4034 DMWalp 26-May-1983
0000 113 : Intergate new logical name structures.
0000 114 :


```
0000 115 : V03-004 TCM0001 Trudy C. Matthews 21-Apr-1982
0000 116 : Call routine EXESDALLOC_DEV to deallocate a device. This
0000 117 : routine handles cluster device deallocation correctly.
0000 118 :
0000 119 : V03-003 PHL0101 Peter H. Lipman 20-Jun-1982
0000 120 : $QIOW now synchronizes the EFN and IOSB parameters
0000 121 : correctly. Eliminate the synchronization code here.
0000 122 :
0000 123 : V03-002 STJ0257 Steven T. Jeffreys, 12-Apr-1982
0000 124 : - Do not mung device allocation access mode.
0000 125 : - Make code AST reentrant. This includes the addition
0000 126 : of the local subroutine DO_10.
0000 127 :
0000 128 : V03-001 STJ0229 Steven T. Jeffreys, 23-Mar-1982
0000 129 : Clear the 'mount verification possible' bit in the VCB
0000 130 : so that $DISMOU will succeed even if no volume is present
0000 131 : in the drive (as in version 2).
0000 132 :
0000 133 : V02-008 ACG0248 Andrew C. Goldstein, 23-Dec-1981 11:56
0000 134 : Fix logical name interlocks
0000 135 :
0000 136 : V02-007 ACG0226 Andrew C. Goldstein, 24-Nov-1981 22:29
0000 137 : Issue IOS_AVAILABLE on DISMOUNT/NOUNLOAD
0000 138 :
0000 139 : V0006 STJ0138 Steven T. Jeffreys, 12-Nov-1981
0000 140 : Use IOC$CVT_DEVNAM to format the device name.
0000 141 :
0000 142 : V0005 ACG0062 Andrew C. Goldstein, 16-Oct-1979 13:53
0000 143 : Unload volumes mounted foreign on dismount
0000 144 :
0000 145 : V0004 ACG0003 Andrew C. Goldstein, 1-Feb-1979 11:07
0000 146 : Add handling of dummy MTL entry for volume set
0000 147 :
0000 148 : Andrew C. Goldstein, 12-Jul-78 20:08
0000 149 : V0003 - ADD ERROR LOG ENTRY FOR FOREIGN DISMOUNT
0000 150 :
0000 151 : **
0000 152 :
0000 153 : Define system control blocks
0000 154 :
0000 155 :
0000 156 : $DDBDEF ; DDB
0000 157 : $DEVDEF ; device characteristics bits
0000 158 : $DCDEF ; define device types
0000 159 : $EMBETDEF ; define error log message codes
0000 160 : $EMBVMDEF ; define error log buffer format
0000 161 : $IODEF ; define I/O function codes
0000 162 : $IPLDEF ; define IPL definitions
0000 163 : $LCKDEF ; define lock manager values
0000 164 : $LKIDEF ; define codes for $GETLKI
0000 165 : $ORBDEF ; object's rights block offsets
0000 166 : $PCBDEF ; process control block
0000 167 : $PRDEF ; processor register codes
0000 168 : $PRVDEF ; privilege bit definitions
0000 169 : $MTLDEF ; mounted volume list entry
0000 170 : $SSDEF ; system service codes
0000 171 : $UCBDEF ; UCB
```

DISMOUNT
V04-000

- DISMOUNT A MOUNTED MASS STORAGE VOLUME 16-SEP-1984 00:02:34 VAX/VMS Macro V04-00
5-SEP-1984 03:41:26 [SYS.SRC]DISMOUNT.MAR;1

Page 4
(1)

```
0000 172          $VCBDEF                      ; VCB
0000 173 ;
0000 174 ; Local storage allocated on stack (addressed off R3)
0000 175 ;
00000020 0000 176 NAME_LENGTH      = 32      ; length of device name buffer
00000000 0000 177 CHANNEL          = 0        ; channel number
00000004 0000 178 DEVICE_NAME      = 4        ; string descriptor of device name
0000000C 0000 179 NAME_STRING      = 12       ; device name string buffer
0000002C 0000 180
0000002C 0000 181 LOCAL_SIZE       = 44       ; total size of stack locals
00000000 0000 182
00000000 0000 183          .PSECT Y$DISMOUNT
```

```
0000 185 :++
0000 186 :
0000 187 : FUNCTIONAL DESCRIPTION:
0000 188 :
0000 189 : This routine dismounts the indicated mounted volume list entry.
0000 190 : The MTL and logical name, if it still exists, are deleted, and the
0000 191 : volume share count is decremented. If the share count goes to
0000 192 : zero, the volume itself is dismounted.
0000 193 :
0000 194 : CALLING SEQUENCE:
0000 195 : JSB IOC$DISMOUNT
0000 196 :
0000 197 : INPUT PARAMETERS:
0000 198 : R3 = LBC to unload volume
0000 199 : LBS to not unload
0000 200 : R4 = address of process PCB
0000 201 : R6 = address of mounted volume list entry
0000 202 :
0000 203 : IMPLICIT INPUTS:
0000 204 : IPL - IPL$_ASTDEL
0000 205 :
0000 206 : OUTPUT PARAMETERS:
0000 207 : R0-R2,R6 smashed, other registers preserved
0000 208 :
0000 209 : IMPLICIT OUTPUTS:
0000 210 : NONE
0000 211 :
0000 212 : ROUTINE VALUE:
0000 213 : SS$_NORMAL,SS$_NOIOCHAN
0000 214 :
0000 215 : SIDE EFFECTS:
0000 216 : Volume dismounted: logical name & MTL deallocated, VCB gone or soon
0000 217 : to go, ACP process may become deleted
0000 218 :
0000 219 :--
0000 220 :
0000 221 :
0000 222 : IOC$DISMOUNT::
0000 223 : PUSH R3,R4,R5 ; save registers
55 0C 38 BB 0000 224 : MOVL MTL$_UCB(R6),R5 ; get UCB address
10 A6 D5 0002 225 : TSTL MTL$_LOGNAME(R6) ; test address of logical name
1F 13 0009 226 : BEQL 10$ ; branch if none
0000 227 : DSBINT S^#IPL$_ASTDEL
00000000'EF 16 0011 228 : JSB LNMSLOCKW ; lock the table
51 10 A6 D0 0017 229 : MOVL MTL$_LOGNAME(R6),R1 ; get address of logical name
00000000'EF 16 001B 230 : JSB LNMSDELETE_LNMB ; delete the logical name
00000000'EF 16 0021 231 : JSB LNMSUNLOCK ; and unlock the table
0027 232 : ENBINT
002A 233 :
7E 0B A6 9A 002A 234 10$: MOVZBL MTL$_STATUS(R6),-(SP) ; save MTL entry status byte
50 56 D0 002E 235 : MOVL R6,R0 ; get MTL address in R0
05 18 0031 236 : BGEQ 20$ ; branch if process space address
FFCA' 30 0033 237 : BSBW EXE$DEAPAGED ; deallocate to system paged pool
OE 11 0036 238 : BRB 30$
53 51 0B A6 3C 0038 239 20$: MOVZWL MTL$_SIZE(R6),R1 ; get block size
00000000'9F DE 003C 240 : MOVAL @#CTL$GQ_ALLOCREG,R3 ; and process allocation list head
FFBA' 30 0043 241 : BSBW EXE$DEALLOCATE ; and deallocate to process pool
```



```
0046 242
0046 243
0046 244 : Now lock the I/O database mutex and decrement the volume share count.
0046 245 : If it goes to zero, mark the UCB for dismount.
0046 246
0046 247
0046 248 30$: ASSUME MTL$V_VOLSET EQ 0
0049 249      BLBS      (SP)+740$      ; branch if MTL entry was for volume set
004C 250      BSBW      SCH$IOLOCKW      ; lock I/O database
0050 251      MOVL      UCB$V_VCB(R5),R0      ; and VCB address
0053 252      DECB      VCB$W_MCOUNT(R0)      ; decrement mount count
0055 253      BEQL      50$      ; branch if now idle
0058 254 40$:      BSBW      SCH$IOUNLOCK      ; else unlock I/O database
005B 255      SETIPL     #0
005E 256      MOVL      #SS$ _NORMAL,R0      ; set success
0061 257      BRW        130$      ; and get out
0061 258 50$:      BBSS      #DEV$V_DMT,UCB$V_DEVCHAR(R5),60$ ; set mark for dismount
0066 259 60$:      BLBC      (SP),70$      ; branch if volume to be unloaded
0069 260      BBCC      #UCB$V_UNLOAD,UCB$W_STS(R5),70$ ; else clear unload bit
006E 261 70$:      BICB2     #<1aVCB$V_MOUNTVER>,- ; clear MV bit in the VCB
0070 262      VCB$B_STATUS2(R0)
0072 263 80$:      BBSC      #UCB$V_MOUNTING,UCB$W_STS(R5),90$ ; clean up status bits
0077 264 90$:      BSBW      SCH$IOUNLOCK      ; unlock the I/O database
007A 265      SETIPL     #0
007D 266
007D 267
007D 268 : Assign a channel to the device. If it is mounted Files-11, issue a dismount
007D 269 : QIO. (If it is mounted foreign, deassigning the channel will complete the
007D 270 : cleanup).
007D 271
007D 272      SUBL      #LOCAL_SIZE,SP      ; allocate local storage on stack
0080 273      MOVL      SP,R3
0083 274      MOVL      #NAME_LENGTH,R0      ; set name buffer length
0086 275      MOVAL     NAME_STRING(R3),R1      ; set name buffer address
008A 276      MOVL      R1,DEVICE_NAME+4(R3) ; copy address to descriptor
008E 277      CLRL      R4      ; get node + device name
0090 278      BSBW      IOC$CVT_DEVNAM      ; format the device name
0093 279      MOVL      R1,DEVICE_NAME(R3)      ; save resultant string length
0097 280      CLRL      CHANNEL(R3)      ; init channel number
0099 281      $ASSIGN_S  CHAN=CHANNEL(R3),- ; and assign a channel to the device
0099 282      DEVNAM=DEVICE_NAME(R3)
00A7 283      BLBC      R0,120$      ; if this fails, we will have a hung device
00AA 284
00AA 285      BBC        #DEV$V_FOR,- ; if BC then not foreign
00AC 286      UCB$V_DEVCHAR(R5),100$ ;
00AF 287      MOVL      LOCAL_SIZE+4(SP),R4 ; recover PCB address
00B3 288      BSBW      FOREIGN      ; dismount foreign device
00B5 289      BRB        110$      ; continue
00B7 290
00B7 291 100$:      PUSHL     #<IOS$ ACPICONTROL!IOSM_DMOUNT>
00BD 292      PUSHL     CHANNEL(R3)      ; push channel number
00BF 293      CALLS      #2,W^DO IO      ; issue the dismount QIO
00C4 294      MOVAQ     DEVICE_NAME(R3),R4 ; get address of device name descriptor
00C8 295      BSBW      DELETE_RUJ      ; delete the recovery unit journal (ruj)
00CB 296 110$:      $DASSGN_S  CHAN=CHANNEL(R3) ; deassign the channel
00D5 297 120$:      ADDL      #LOCAL_SIZE,SP ; restore stack pointer
00D8 298
```

DISMOUNT
V04-000

- DISMOUNT A MOUNTED MASS STORAGE VOLUME 16-SEP-1984 00:02:34 VAX/VMS Macro V04-00
5-SEP-1984 03:41:26 [SYS.SRC]DISMOUNT.MAR;1

Page 7
(2)

38 BA 00D8 299 130\$: POPR #^M<R3,R4,R5> ; restore registers
05 00DA 300 RSB

```
00DB 302 .SBTTL DISMOUNT FOREIGN DEVICE
00DB 303
00DB 304 : Foreign devices are dismantled on the spot, with no interlock checks.
00DB 305 : The reason for this is that the only event we could defer the dismant
00DB 306 : to is last channel deassign, which is not a suitable location.
00DB 307
00DB 308 : Construct and send the error log message signalling dismant.
00DB 309
00DB 310
00DB 311 .ENABLE LSB
00DB 312 FOREIGN:
00DB 313 MOVZBL #EMBSK_VM_LENGTH,R1 : dismant foreign device
00DB 314 BSBW ERL$ALOCEMB : length of error log message
00DB 315 BLBC R0,10$ : allocate an error log buffer
00DB 316 : branch if failure
00DB 317
00DB 318 PUSHB #^M<R2,R3,R4,R5> : save address of buffer and R3, R4, R5
00DB 319 ASSUME EMB$VM_ERRCNT EQ EMB$VM_OWNUI+4
00DB 320 ASSUME EMB$VM_OPRCNT EQ EMB$VM_ERRCNT+4
00DB 321 ASSUME EMB$VM_UNIT EQ EMB$VM_OPRCNT+4
00DB 322 ASSUME EMB$VM_NAMLNG EQ EMB$VM_UNIT+2
00DB 323 ASSUME EMB$VM_NAMTXT EQ EMB$VM_NAMLNG+1
00DB 324 ASSUME EMB$VM_VOLNUM EQ EMB$VM_NAMTXT+15
00DB 325 ASSUME EMB$VM_NUMSET EQ EMB$VM_VOLNUM+2
00DB 326 ASSUME EMB$VM_LABEL EQ EMB$VM_NUMSET+2
00DB 327
00DB 328 MOVW #EMBSK_VD,EMB$VM_ENTRY(R2) : message code = dismant
00DB 329 ADDL #EMB$VM_OWNUI,R2 : point to entries to be filled in
00DB 330 MOVL UCBSL_ORB(R5),R0 : get ORB address
00DB 331 MOVL ORBSL_OWNER(R0),(R2)+ : volume owner UIC
00DB 332 MOVL UCBSL_ERRCNT(R5),(R2)+ : volume error count
00DB 333 MOVL UCBSL_OPCNT(R5),(R2)+ : volume operation count
00DB 334 MOVW UCBSL_UNIT(R5),(R2)+ : unit number
00DB 335 ADDL3 #VCBSL_VOLNAME,UCBSL_VCB(R5),-(SP) : save address of volume label
00DB 336 ADDL3 UCBSL_DDB(R5),#DDB$NAME,R6 : calculate device name address
00DB 337 MOVZBL (R6),R0 : get length of device name
00DB 338 INCL R0 : bump to include count byte
00DB 339 MOVCS R0,(R6),#0,#16,(R2) : copy device name into message
00DB 340 CLRL (R3)+ : zero rel vol number and volume set size
00DB 341 MOVCS #12,@(SP)+,(R3) : copy volume label
00DB 342 POPR #^M<R2> : recover buffer address
00DB 343 BSBW ERL$RELEASEMB : release error log buffer and send
00DB 344 POPR #^M<R3,R4,R5>
00DB 345
00DB 346 : Release the device, using an unload and/or available function,
00DB 347 : depending on whether the volume is supposed to be unloaded or not.
00DB 348
00DB 349 10$: CLRL R2 : assume privilege bit clear
00DB 350 BBCC #PRV$V_PHY_IO,PCBSQ_PRIV(R4),20$ : set PHY_IO privilege and test
00DB 351 INCL R2 : bit was set - save state
00DB 352 20$: BBCC #UCBSV_UNLOAD,UCBSW_STS(R5),30$ : branch if no unload
00DB 353 PUSHB #10$ UNLOAD : set up for unload
00DB 354 PUSHB CHANNEL(R3) : push channel number
00DB 355 CALLS #2,W^DO IO : issue the unload or rewind QIO
00DB 356 30$: PUSHB #10$ AVAILABLE : now release drive
00DB 357 PUSHB CHANNEL(R3) : push channel number
00DB 358 CALLS #2,W^DO IO : issue the unload or rewind QIO
00DB 359 INSV R2,#PRV$V_PHY_IO,#1,PCBSQ_PRIV(R4) : restore privilege bit
```



```
0800 8F AA 014D 359 BICW #UCBSM_VALID,- ; clear software volume valid.
64 A5 0151 360 UCBSM_STS(R5)
0153 361
0153 362
0153 363
0153 364
0153 365
0088 8F BB 0153 365 PUSHR #M<R3,R7> ; save R3 & R7
34 A5 D0 0157 366 MOVL UCBSL_VCB(R5),R7 ; get VCB address
5E 18 C2 015B 367 SUBL #24,SP ; allocate lock status block on stack
56 5E D0 015E 368 MOVL SP,R6
04 A6 20 A5 D0 0161 369 MOVL UCBSL_LOCKID(R5),4(R6) ; get device lock ID
6C 13 0166 370 BEQL 50$ ; branch if none - not cluster dev
61 38 A5 17 E0 0168 371 BBS #DEVSV_ALL,UCBSL_DEVCHAR(R5),40$ ; branch if dev allocated
50 04 D0 016D 372 MOVL #LCK$K_PWMODE,R0 ; otherwise raise lock to PW
0170 373 $ENQW_S LKMODE=R0,- ; queue for the device lock
0170 374 LKSB=(R6),-
0170 375 EFN=S^#EXESC_SYSEFN,-
0170 376 FLAGS=#LCK$M_CONVERT!LCK$M_VALBLK!LCK$M_SYNCSTS!LCK$M_NOQUOTA
61 50 E9 0189 377 BLBC R0,LOCKERR ; bug check if error
09 66 E8 018C 378 BLBS (R6),35$
09F0 8F 66 B1 018F 379 CMPW (R6),#SS$_VALNOTVALID ; Is the error simply value block not valid?
02 13 0194 380 BEQL 35$ ; No problem.
55 11 0196 381 BRB LOCKERR ; Problem.
0198 382
0198 383
0198 384
0198 385
0198 386 35$: CLRL -(SP) ; longword for lock count
019A 387 CLRQ -(SP) ; item list end + retlen
08 AE 9F 019C 388 PUSHAB 8(SP) ; address of block count
02050004 8F DD 019F 389 PUSHL #LKIS_LCKCOUNT@16!4 ; size & item code for lock count
51 5E D0 01A5 390 MOVL SP,R1 ; item list address
7E 7C 01A8 391 CLRQ -(SP) ; IOSB
50 5E D0 01AA 392 MOVL SP,R0
01AD 393 $GETLKIW_S LKIDADR=VCBSL_VOLLKID(R7),-
01AD 394 ITMLST=(R1),-
01AD 395 EFN=S^#EXESC_SYSEFN,-
01AD 396 IOSB=(R0)
29 50 E9 01C1 397 BLBC R0,LOCKERR ; bug check if error
26 6E E9 01C4 398 BLBC (SP),LOCKERR
5E 18 C0 01C7 399 ADDL #24,SP ; clean IOSB & item list off stack
8E D7 01CA 400 DECL (SP)+ ; check lock count against 1
06 12 01CC 401 BNEQ 50$ ; branch if other mounts exist
08 A6 7C 01CE 402 CLRQ 8(R6) ; last mount - clear value block
10 A6 7C 01D1 403 CLRQ 16(R6)
01D4 404
01D4 405
01D4 406
01D4 407
01D4 408 50$: BSBW SCH$IOLOCKW ; take I/O database mutex
7C A7 D0 01D7 409 MOVL VCB$S_VOLLKID(R7),R0 ; get volume lock ID
14 13 01DB 410 BEQL 60$ ; branch if none
01DD 411 $DEQ_S LKID=R0 ; release it
04 50 E8 01EA 412 BLBS R0,60$ ; branch if OK
01ED 413
01ED 414
01ED 415
: To here on any errors from lock management services.
```

```
01ED 416 LOCKERR:
01ED 417          BUG_CHECK XQPERR,FATAL          ; unexpected lock manager error
01F1 418          ;
01F1 419          ; Clear out the UCB.
01F1 420          ;
CA 01F1 421 60$: BICL    #<DEVSM_DMT!DEVSM_FOR!- ; clear marked for dismount, foreign,
01F2 422          DEVSM_RCK!DEVSM_WCK!- ; read/write check,
01F2 423          DEVSM_SWL!DEVSM_MNT>,- ; software write locked, and mounted
01F2 424          UCBSL_DEVCHAR(R5) ; status bit.
01F9 425          DECB    UCBSW_REFC(R5) ; remove mount from ref count
01FC 426          MOVL    R7,R0 ; get address of VCB.
01FF 427          CLRL    UCBSL_VCB(R5) ; clear address of VCB.
0202 428          BSBW    EXESDEANONPAGED ; deallocate VCB.
0205 429          MOVL    UCBSL_ORB(R5),R0 ; get the ORB address
0209 430          ;
0209 431          ASSUME    ORBSL_OWN_PROT EQ ORBSL_SYS_PROT+4
0209 432          ASSUME    ORBSL_WOR_PROT EQ ORBSL_GRP_PROT+4
0209 433          ;
18 A0 7C 0209 434          CLRQ    ORBSL_SYS_PROT(R0) ; clear out stale protection info
20 A0 7C 020C 435          CLRQ    ORBSL_GRP_PROT(R0)
60 D4 020F 436          CLRL    ORBSL_OWNER(R0) ; clear out stale owner also
0211 437          ;
0211 438          ; Release the device lock with the updated value block.
0211 439          ;
04 A6 D5 0211 440          TSTL    4(R6) ; check if we have a lock ID
2E 13 0214 441          BEQL    80$ ; branch if no lock
50 01 D0 0216 442          MOVL    #LCK$K_CRMODE,R0 ; use CR mode if not allocated
03 38 A5 17 E1 0219 443          BBC    #DEVSV_ALL,UCBSL_DEVCHAR(R5),70$ ; branch if not allocated
50 05 D0 021E 444          MOVL    #LCK$K_EXMODE,R0 ; use EX mode if allocated
0221 445 70$: $ENQW_S LKMODE=R0,- ; convert the device lock down
0221 446          LKSB=(R6),- ; writing possibly modified value block
0221 447          EFN=S^#EXES$C SYSEFN,-
0221 448          FLAGS=#LCK$M_CONVERT!LCK$M_CVTSYS!LCK$M_VALBLK!LCK$M_SYNCSTS!LCK$M_NOQUOTA
023E 449          ; Sorry about the tacky format above, but the assembler won't parse
023E 450          ; macro args broken across lines.
AC 50 E9 023E 451          BLBC    R0,LOCKERR ; bug check if error
A9 66 E9 0241 452          BLBC    (R6),LOCKERR
0244 453          ;
0244 454          ; Call routine to deallocate the device when appropriate
0244 455          ;
FDB9' 30 0244 456 80$: BSBW    IOC$DALLOC_DMT ; complete the deallocation now
0247 457          ;
FDB6' 30 0247 458 90$: BSBW    SCH$IOUNLOCK ; release the I/O database mutex
024A 459          SETIPL    #0 ; and drop IPL
5E 18 C0 024D 460          ADDL    #24,SP ; clean the stack
0088 8F BA 0250 461          POPR    #^M<R3,R7> ; restore R3 & R7
05 D5 0254 462          RSB
0255 463          ;
0255 464          .DISABLE LSB
```

```
0255 466 .SBTTL DO_IO - COMMON I/O ROUTINE
0255 467 ++
0255 468 DO_IO
0255 469
0255 470 FUNCTIONAL DESCRIPTION:
0255 471
0255 472 This routine is an envelope procedure for all I/O done by this
0255 473 module. Use a system event flag for the I/O. Since $QIOW now
0255 474 properly waits for the combination of the event flag and IOSB
0255 475 to be set, no special synchronization is needed here.
0255 476
0255 477 INPUT:
0255 478
0255 479 CHAN(AP) = channel number to use for the I/O
0255 480 FUNC(AP) = I/O function code
0255 481
0255 482 OUTPUT:
0255 483
0255 484 NONE.
0255 485
0255 486 ROUTINE VALUE:
0255 487
0255 488 R0 = some system status code
0255 489 --
0255 490
0255 491 Useful symbols
0255 492
0255 493
0255 494
00000004 0255 495 CHAN = 4 ; offset to channel number
00000008 0255 496 FUNC = 8 ; offset to I/O function code
0255 497
0255 498
52 7E 0004 0255 499 DO_IO: .WORD *M(R2) ; common I/O routine
0257 500 MOVAQ -(SP),R2 ; reserve IOSB, address to R2
025A 501 $QIOW_S EFN=S^#EXESC SYSEFN,- ; use system event flag
025A 502 CHAN=CHAN(AP),- ; use channel supplied by caller
025A 503 FUNC=FUNC(AP),- ; use function code supplied by caller
025A 504 IOSB=(R2) ; use local IOSB
03 50 E9 0277 505 BLBC R0,10$ ; branch if error
50 62 3C 027A 506 MOVZWL (R2),R0 ; set the return status in R0
04 027D 507 10$: RET ; return
```



```
027E 509 .SBTTL DELETE_RUJ - DELETE RECOVERY UNIT JOURNAL
027E 510 :++
027E 511 :DELETE_RUJ
027E 512 :
027E 513 :FUNCTIONAL DESCRIPTION:
027E 514 :
027E 515 :Delete the recovery unit journal on this volume.
027E 516 :Failure to do so will leave the journal file open
027E 517 :and the device marked for dismount. This routine
027E 518 :must be called after the dismount $QIO has been
027E 519 :sent to the ACP.
027E 520 :
027E 521 :INPUT:
027E 522 :
027E 523 :R4 = address of device name descriptor
027E 524 :R5 = device UCB address
027E 525 :
027E 526 :OUTPUT:
027E 527 :
027E 528 :NONE. (Contents of R0 and R1 are unpredictable)
027E 529 :
027E 530 :ROUTINE VALUE:
027E 531 :
027E 532 :NONE.
027E 533 :--
027E 534 :
027E 535 DELETE_RUJ: ; delete recovery unit journal
027E 536 BBS ; only disks have RUJ's
0280 537 #DEV$V SQD,-
0283 538 UCB$$_DEVCHAR(R5),20$
0283 539 :
0283 540 :Assign a channel to the RUJ. If the service fails,
0283 541 :exit immediately, as it means that no RUJ is active.
0283 542 :
0283 543 PUSH R2 ; save R2 and make local storage
0285 544 SP,R2 ; save SP
0288 545 $ASSJNL_S CHAN = (R2),- ; channel to journal
0288 546 JNL_TYP = #DT$_RUJNL,- ; journal type
0288 547 DEVNAM = (R4) ; device name descriptor
02A4 548 BLBC R0,10$ ; branch if error
02A7 549 :
02A7 550 :Delete the journal. The channel to the journal is
02A7 551 :deassigned in the process.
02A7 552 :
02B3 553 $DELJNL_S CHAN = (R2) ; delete the journal
02B6 554 BLBS R0,10$ ; if success then deljnl
02B6 555 : deassigned the channel for us
02C2 556 $DEASJNL_S CHAN = (R2) ; deassign the journal channel
02C4 557 POPR #^M<R0,R2> ; restore stack
02C5 558 RSB ; return
02C5 559
02C5 560 .END
```

41 38 05 E0
52 5E BB
1B 50 E9
0C 50 E8
05 BA
05

DISMOUNT
Symbol tableE 4
- DISMOUNT A MOUNTED MASS STORAGE VOLUME 16-SEP-1984 00:02:34 VAX/VMS Macro V04-00
5-SEP-1984 03:41:26 [SYS.SRC]DISMOUNT.MAR;1Page 13
(5)

SST1 = 00000000
BUGS_XQPERR ***** X 02
CHAN = 00000004
CHANNEL = 00000000
CJFSASSJNL ***** GX 02
CJFSDEASJNL ***** GX 02
CJFSDELJNL ***** GX 02
CTL\$GQ_ALLOCREG ***** X 02
DDB\$T_NAME = 00000014
DELETE_RUJ 0000027E R 02
DEV\$M_DMT = 00200000
DEV\$M_FOR = 01000000
DEV\$M_MNT = 00080000
DEV\$M_RCK = 40000000
DEV\$M_SWL = 02000000
DEV\$M_WCK = 80000000
DEV\$V_ALL = 00000017
DEV\$V_DMT = 00000015
DEV\$V_FOR = 00000018
DEV\$V_SQD = 00000005
DEVICE_NAME = 00000004
DO_IO 00000255 R 02
DT\$ RUJNL = 00000001
EMBSB_VM_NAMLNG = 0000001E
EMBSK_VD = 00000041
EMBSK_VM_LENGTH = 0000003E
EMBSL_VM_ERRCNT = 00000014
EMBSL_VM_OPRCNT = 00000018
EMBSL_VM_OWNUIC = 00000010
EMBST_VM_LABEL = 00000032
EMBST_VM_NAMTXI = 0000001F
EMBSW_VM_ENTRY = 00000004
EMBSW_VM_NUMSET = 00000030
EMBSW_VM_UNIT = 0000001C
EMBSW_VM_VOLNUM = 0000002E
ERL\$ACLOCMB ***** X 02
ERL\$RELEASEMB ***** X 02
EXESC_SYSEFN ***** X 02
EXESDEALLOCATE ***** X 02
EXESDEANONPAGED ***** X 02
EXESDEAPAGED ***** X 02
FOREIGN 000000DB R 02
FUNC = 00000008
IOSM_DMOUNT = 00000400
IOS_ACPCONTROL = 00000038
IOS_AVAILABLE = 00000011
IOS_UNLOAD = 00000001
IOC\$CVT_DEVNAM ***** X 02
IOC\$DALLOC_DMT ***** X 02
IOC\$DISMOUNT 00000000 RG 02
IPL\$ASTDEL = 00000002
LCK\$R_CRMODE = 00000001
LCK\$K_EXMODE = 00000005
LCK\$K_PWMODE = 00000004
LCK\$M_CONVERT = 00000002
LCK\$M_CVTSYS = 00000040
LCK\$M_NOQUOTA = 00000020

LCK\$M_SYNCSTS = 00000008
LCK\$M_VALBLK = 00000001
LKIS_CKCOUNT = 00000205
LNMSDELETE_LNMB ***** X 02
LNMSLOCKW ***** X 02
LNMSUNLOCK ***** X 02
LOCAL_SIZE = 0000002C
LOCKERR 000001ED R 02
MTLSB_STATUS = 0000000B
MTLSL_LOGNAME = 00000010
MTLSL_UCB = 0000000C
MTLSV_VOLSET = 00000000
MTLSW_SIZE = 00000008
NAME_LENGTH = 00000020
NAME_STRING = 0000000C
ORBSL_GRP_PROT = 00000020
ORBSL_OWNER = 00000000
ORBSL_OWN_PROT = 0000001C
ORBSL_SYS_PROT = 00000018
ORBSL_WOR_PROT = 00000024
PCBSQ_PRIV = 00000084
PRS_IPL = 00000012
PRV\$V_PHY_IO = 00000016
SCH\$IOLOCKW ***** X 02
SCH\$IOUNLOCK ***** X 02
SS\$NORMAL = 00000001
SS\$VALNOTVALID = 000009F0
SYSS\$ASSIGN ***** GX 02
SYSS\$DASSGN ***** GX 02
SYSS\$DEQ ***** GX 02
SYSS\$ENQW ***** GX 02
SYSS\$GETLKIW ***** GX 02
SYSS\$QIOW ***** GX 02
UCBSL_DDB = 00000028
UCBSL_DEVCHAR = 00000038
UCBSL_LOCKID = 00000020
UCBSL_OPCNT = 00000070
UCBSL_ORB = 0000001C
UCBSL_VCB = 00000034
UCBSM_VALID = 00000800
UCBSV_MOUNTING = 00000009
UCBSV_UNLOAD = 0000000C
UCBSW_ERRCNT = 00000082
UCBSW_REFC = 0000005C
UCBSW_STS = 00000064
UCBSW_UNIT = 00000054
VCBSB_STATUS2 = 00000053
VCBSL_VOLLKID = 0000007C
VCBST_VOLNAME = 00000014
VCBSV_MOUNTVER = 00000002
VCBSW_MCOUNT = 0000004C

+-----+
! Psect synopsis !
+-----+

PSECT name	Allocation	PSECT No.	Attributes
. ABS .	00000000 (0.)	00 (0.)	NOPIC USR CON ABS LCL NOSHR NOEXE NORD NOWRT NOVEC BYTE
\$ABSS\$	00000000 (0.)	01 (1.)	NOPIC USR CON ABS LCL NOSHR EXE RD WRT NOVEC BYTE
Y\$DISMOUNT	000002C5 (709.)	02 (2.)	NOPIC USR CON REL LCL NOSHR EXE RD WRT NOVEC BYTE

+-----+
! Performance indicators !
+-----+

Phase	Page faults	CPU Time	Elapsed Time
Initialization	29	00:00:00.09	00:00:01.35
Command processing	115	00:00:00.54	00:00:04.35
Pass 1	493	00:00:19.98	00:01:03.98
Symbol table sort	1	00:00:03.25	00:00:10.29
Pass 2	115	00:00:03.44	00:00:10.17
Symbol table output	13	00:00:00.12	00:00:00.53
Psect synopsis output	2	00:00:00.02	00:00:00.02
Cross-reference output	0	00:00:00.00	00:00:00.00
Assembler run totals	770	00:00:27.44	00:01:30.69

The working set limit was 1650 pages.
113983 bytes (223 pages) of virtual memory were used to buffer the intermediate code.
There were 120 pages of symbol table space allocated to hold 2155 non-local and 26 local symbols.
560 source lines were read in Pass 1, producing 15 object records in Pass 2.
42 pages of virtual memory were used to define 41 macros.

+-----+
! Macro library statistics !
+-----+

Macro library name	Macros defined
\$255\$DUA28:[SYS.OBJ]LIB.MLB;1	13
\$255\$DUA28:[SYSLIB]STARLET.MLB;2	25
TOTALS (all libraries)	38

2412 GETS were required to define 38 macros.

There were no errors, warnings or information messages.

MACRO/LIS=LIS\$:DISMOUNT/OBJ=OBJ\$:DISMOUNT MSRC\$:DISMOUNT/UPDATE=(ENH\$:DISMOUNT)+EXECMLS/LIB

0374 AH-BT13A-SE
VAX/VMS V4.0

DIGITAL EQUIPMENT CORPORATION
CONFIDENTIAL AND PROPRIETARY

